# Documentation

Version: {docversion}

# **Table of Contents**

1.	Introd	uction	. 1
	1.1.	Overview	. 1
	1.2.	Files and Folder structure	. 2
2.	Quick	start example	. 5
3.	Drive	r	10
	3.1.	File Driver	10
	3.2.	HTTP Driver	11
4.	Sourc	e	13
	4.1.	File Source	13
	4.2.	HTTP Source	14
	4.3.	JDBC Source	15
	4.4.	Merge Source	18
	4.5.	Script Source	19
	4.6.	XLS Source	19
	4.7.	OCS Source	21
		4.7.1. General OCS Parameters	21
		4.7.2. Using a source for OCS computers	22
		4.7.3. Using a source for OCS SNMP devices	22
		4.7.4. Using a mock source for development	22
5.	Марр	er	24
	5.1.	No-operation echo mapper	24
	5.2.	Empty requisition mapper	24
	5.3.	OCS Mapper	24
		5.3.1. OCS Computers	25
		5.3.2. OCS SNMP Devices	26
		5.3.3. Black- and Whitelists	26
	5.4.	Script mapper	28
6.	Asset	field mapping	29
7.	Script	Steps	32
8.	Docur	mentation guidelines	38
	8.1.	Overall Flow	39
	8.2.	Important files and folders	39
	8.3.	Headings and document structure	40
	8.4.	Writing	40
	8.5.	Gotchas	40
	8.6	Links	41

#### Documentation

8.7. Text Formatting	42
8.8. Admonitions	42
8.9. Images	43
8.9.1. Images Files	43
8.10. Attributes	44
8.11. Comments	44
8.12. Code Snippets	45
8.12.1. Explicitly defined in the document	45
8.12.2. Fetched from source code	46

# **List of Figures**

1.1. OpenNMS PRIS overview	1
2.1. Worksheet with Router	5
2.2. Worksheet with Server	6
2.3. Output of PRIS server for both configured requisitions	8
8.1	43
8.2 example odp	44

# Chapter 1. Introduction

If you have a large network and discovery doesn't help, it helps to find a source of truth for starting to fill your management system. The provisioning integration server *PRIS* is a software which helps you to integrate OpenNMS to single or multiple external inventory systems. It gives you several steps to integrate, transform, clean up, and merge your extracted data before you provide the data into OpenNMS. The result of *PRIS* is the OpenNMS requisition model which can be read from OpenNMS Provisiond.

The service is used to provide an integration point for *OpenNMS* external inventories or home brew inventories. With pris the data is normalized to the *OpenNMS* requisition model and can be consumed from *OpenNMS provisiond*. It is highly specialized to enrich the requisition model with *SNMP* information i.e. *SNMP* interfaces, generic *SNMP* attributes like system location, system contact, and system description. Besides that, *Provisiond* can also run service detectors against IP interfaces and allows to run policies to control the monitoring behavior. *Pris* is an instance in front of *Provisiond*, it allows to aggregate information from different sources and manipulate them in a flexible way.

The output from *PRIS* is provided as *XML* over *HTTP* and can be used in *Provisiond* to import and discover services and SNMP data from. In OpenNMS a requisition is a set of nodes (networked devices) that you want to import into OpenNMS for monitoring and management. You can assign in OpenNMS services, detectors and policies to model the network monitoring behavior. For this reason a good practice is to organize nodes with a similar network monitoring profile in a requisition. The *PRIS* components are shown in Section 1.1, "Overview".

# 1.1. Overview




Figure 1.1. OpenNMS PRIS overview

The components from left to right are described as followed:

- OpenNMS Provisiond: This is the internal daemon responsible to get nodes (networked devices) into OpenNMS. Provisiond scans for SNMP information, network services and has to model the network monitoring behavior for OpenNMS.
- **Driver**: The driver is the method how to present the data from *PRIS* to *OpenNMS*. It is only possible to configure *one* driver per *PRIS* instance
- **OpenNMS Requisition**: The data model which has to be built inside of *PRIS*. This is the shared model between *OpenNMS* and *PRIS*.
- Requisition configuration: The description of the integration of your external datasource. A requisition configuration defines which source should be used or which scripts should be applied to modify or transform the data before they are provided into OpenNMS Provisiond.
- Mapper Script: The mapper script is the last script executed before the generated requisition goes to OpenNMS Provisiond through the driver. You can use a mapper script to enrich the requisition, remove nodes or replace OpenNMS requisition node attributes.
- Custom Scripts: In some cases an external inventory has its own data model, e.g.
  OCS Inventory. The script source can be used to map the external inventory-specific
  model into the OpenNMS requisition model.
- **Source**: This is the specific implementation retrieving the data for from your external inventory.
- External Inventory: The inventory from which you want to import data for OpenNMS. It could be a free application like phpIPAM, idoIT, ITIL ticket system like OTRS, a simple spreadsheet or just another OpenNMS instance.

## 1.2. Files and Folder structure

The latest release of *PRIS* can be downloaded from the github release page of the project. It is recommended to extract the tar.gz content to /opt/opennms-pris. The examples and the documentation are built based on this file structure. It is possible to install *PRIS* in a different directory, but you have to take care about adapting the paths in this documentation.

After extracting the archive the file structure should look like this:

<sup>1</sup> https://github.com/OpenNMS/opennms-provisioning-integration-server/releases

```
### documentation 1
### examples 2
   ### fileExample
   ### httpExample
  ### jdbcExample
   ### mergeExample
  ### ocsExample
   ### scriptExample
   ### xlsExample
### global.properties 3
### lib 4
### opennms-pris.jar 5
### opennms-pris.service 6
### opennms-pris.sh 7
### opennms-pris.bat 3
### requisitions 9
### scriptsteps 10
   ### custom 11
    ### default 12
```

- This documentation in HTML format; if you run *PRIS* in HTTP mode you can access the documentation at http://<your-ip>:<port>/documentation
- Configuration examples for requisitions for every available source
- Default configuration for *PRIS* to run in HTTP mode on port 8000
- Libraries for the different sources which can be used with PRIS
- Main application file
- 6 Init script for CentOS or Debian systems running in HTTP mode
- Start script to run PRIS on a Linux console
- Start script to run PRIS on a Windows
- Onfiguration directory for all requisitions to integrate inventories
- Default folder for scripts which are used in requisition configurations to manipulate the inventory import
- Drop-in for your custom created scripts
- 12 Drop-in for default ready to use scripts

PRIS needs at minimum two configuration files. The first is called global.properties, and controls the general behavior of the provisioning integration server. A requisition is just a directory in the application server directory requisitions and has to contain a file called requisition.properties. The directory name is used to access the requisition.

You can create multiple requisitions using different sources, by creating a directory for each requisition with a requisition.properties inside. The global.properties, the requisitions directory and the start script has to be in the same folder. By default we suggest to install your *PRIS* archive to /opt/opennms-pris. If you want to provide the *OpenNMS* requisitions via *HTTP* from the built-in *Jetty* web server as a background daemon, you can use the init script in opennms-pris/src/examples/opennms-pris.

# Chapter 2. Quickstart example

To give an example we want to provide two requisitions from an poor man's inventory as *XLS file* (myInventory.xls). The first requisition has a worksheet containing all routers and the second worksheet has all servers of our network. This example can be found in examples/source/xlsExample.





Figure 2.1. Worksheet with Router

In line 5, 6 and 7 there is a router defined with more than one IP interface. All three interfaces will be manually provisioned. The private IP interface with 192.168.30.1 is not used for SNMP agent communication. The services ICMP, SNMP and StrafePing are forced on some IP interfaces. For all other IP interfaces you can use the OpenNMS Provisiond mechanism scanning IP interface table from SNMP and the detectors for additional services. The server will also be categorized in *Backbone* and *Office*.



#### Figure 2.2. Worksheet with Server

The *OpenNMS* requisition should be provided via *HTTP* and we use *OpenNMS Provisiond* to synchronize it on a regular basis. We build the following file structure:

#### File structure with two requisitions using a single spreadsheet

```
[root@localhost opennms-pris] # pwd && tree
/opt/opennms-pris
### documentation
### examples
### global.properties
### lib
### opennms-pris.jar
### opennms-pris.service
### opennms-pris.sh
### requisitions/
    ### myInventory.xls
    ### myRouter
        ### requisition.properties
    ### myServer
        ### requisition.properties
### scriptsteps
    ### custom
    ### default
```

Providing the *OpenNMS requisition* over *HTTP* we create the following global.properties

#### Use the HTTP web server

```
### File: global.properties
# Start web server
# The web server listens on all interfaces and can be accessed on TCP port
8000
# URL: http://${your-ip}:8000/requisitions/${name-requisition-cfg}

driver = http
host = 0.0.0.0
port = 8000
```

The HTTP server listens on localhost port 8000/TCP. We have to create two directories, myServer and myRouter, each containing a requisition.properties file. Both requisition.properties files reference the main myInventory.xls file which contains two worksheets named myServer and myRouter. The requisition.properties is the same for both requisitions. It is possible to create different script or mapping steps for each requisition.


#### Configuration of the myRouter requisition

```
### File: myRouter/requisition.properties
# This example imports devices from a spreadsheet
# named "myRouter" from the myInventory.xls file
# Path to the XLS fils is relative to
# requisitions.properties
source = xls
source.file = ../myInventory.xls
### default no-operation mapper
mapper = echo
```

#### Configuration of the myServer requisition

```
### File: myRouter/requisition.properties
# This example imports devices from a spreadsheet
# named "myRouter" from the myInventory.xls file
# Path to the XLS fils is relative to
# requisitions.properties
source = xls
source.file = ../myInventory.xls
### default no-operation mapper
mapper = echo
```

It is not necessary to restart the *PRIS* server if you change properties files or the *XLS* file. All changes will be applied from the next request against the server. With the given configuration you see the result of the OpenNMS requisitions with the URL http://localhost:8000/requisitions/myRouter and http://localhost:8000/requisitions/myServer which can be used in *OpenNMS Provisiond*.



# Figure 2.3. Output of PRIS server for both configured requisitions

To get the requisition provided from *PRIS* automatically into OpenNMS you can configure Provisiond with a schedule. Create following to entries in provisiond-configuration.xml and they will automatically be synchronized every night at 0h:0m:0s and 1h:0m:0s.

#### Configuration from OpenNMS Provisiond with provisiond-configuration.xml

```
<requisition-def import-name="myRouter" import-url-resource="http://
localhost:8000/requisitions/myRouter">
        <cron-schedule>0 0 0 * * ? *</cron-schedule>
        </requisition-def>

<requisition-def import-name="myServer" import-url-resource="http://
localhost:8000/requisitions/myServer">
        <cron-schedule>0 0 1 * * ? *</cron-schedule>
```

# Quickstart example

# Chapter 3. Driver

The driver determines how to provide the generated OpenNMS requisition. It is a required global configuration item for the *PRIS* server. The configuration for the drivers has to be specified in the global.properties file. It is possible to configure exactly one driver for the *PRIS* server. For the *PRIS* server you can configure a global log level. The loglevel is also located in the global.properties file and can be configured with the following values:

loglevel = INFO

Level	Default
ALL	
TRACE	
DEBUG	
INFO	*
WARN	
ERROR	
OFF	



Changing the log level requires a restart if you run PRIS as a daemon in HTTP mode.

The driver is configured in global.properties which is located in the root application directory.

/opt/opennms-pris
### global.properties

#### 3.1. File Driver

This driver offers the ability to generate an OpenNMS requisition directly into the filesystem. To use the *file driver* you have to set the parameters in the global.properties:

Para Reception			
driver*	set to file to generate OpenNMS requisitions as XML file		
target*	path/to/output/folder for XML files to generate		
requisiti	oparameter as Java regular expression filter for the requisition name		

#### Example configuration for a file based requisition

```
### File: global.properties
# Generate an requisition and create an requisition file to target
# Create a file for all requisitions matching * (Java regular expression)

loglevel = INFO
driver = file
target = /my/output/folder
requisitions = *
```

#### 3.2. HTTP Driver

The HTTP driver starts *PRIS* as a web server to provide the OpenNMS requisition over HTTP.

Para Reequire	edDescription
driver*	set to http run as web server and provide requisitions over HTTP
host *	Network interface for listening, e.g. 0.0.0.0 = all, 127.0.0.1 = localhost
port *	TCP port to listen for incoming requests. Default is 8000

Access to the requisition can be tested with a browser to URL http://<your-ip>:<port>8000/requisitions/<name-requisition-cfg>. The path *name-requisition-cfg* is the folder name which runs the requisition configuration located in your *PRIS* server directory.

#### Example configuration for a web server provided requisition

```
### File: global.properties
# Start web server
# The web server listens on all interfaces and can be accessed on TCP port
8000
# URL: http://${your-ip}:8000/requisitions/${name-requisition-cfg}
driver = http
```

host = 0.0.0.0 port = 8000

# Chapter 4. Source

A Source is used to get the data to build an *OpenNMS requisition*. Each requisition requires a source definition in the requisition.properties file. Depending on the type of the source, different configuration parameters are available. A JDBC source, for example, has different configuration parameters versus an XLS source. The existing sources with their respective configuration parameters are described in this section.

A source is configured in the requisition.properties for the requisition.

```
/opt/opennms-pris
### requisitions
### myRequisitionConfiguration
### requisition.properties
```

## 4.1. File Source

The file source allows to read a requisition file from the filesystem.

Para Reequire	edDescription
source*	Set file to use this source for the requisition configuration
source:fi	leelative path from requisitions.properties to the OpenNMS requisition xml file
mapper*	Mapper script changing the requisition. For no operation use echo, apply a Groovy script set to script
mapper.fi	lleset mapper is set to script, relative path to your groovy script for modifying the requisition

This source reads an already-defined requisition from an XML file. The file to read has to be a valid OpenNMS requisition already.

#### Example configuration for a file-based requisition

```
### File: myFileRequisition/requisition.properties
# This example uses a predefined OpenNMS requisition
# Path to the myCustomRequisitionFile.xml is relative
# to the requisitions.properties
source = file
source.file = myCustomRequisitionFile.xml
```

```
### default no-operation mapper
mapper = echo
```

# 4.2. HTTP Source

This source is similar to the *file* source. Instead of reading from a local file, it can read a requisition via *HTTP* from another *OpenNMS* instance. The location for the requisition is given by an OpenNMS provisioning ReST URL. It is possible to provide authentication credentials to be able to consume the ReST service.

Para Receptaire	edDescription
source*	Set http to use this source for the requisition configuration
source:ur	1OpenNMS requisition ReST service base URL, e.g. http://demo.opennms.org/opennms/rest/requisitions
source.us	e penNMS user name for accessing the requisition ReST URL
source.pa	s@penMMS user password for accessing the requisition ReST URL
mapper*	Mapper script for changing the requisition. For no operation use echo; to apply a JSR-223 script set to script
mapper.fi	Meset mapper is set to script, relative path to your JSR-223 script for modifying the requisition

The given example configuration reads the requisition from the publicly available OpenNMS demo system.

#### **Example configuration for an HTTP-based requisition**

```
### File: opennmsdemo/requisition.properties
# This example reads imports the requisition name Latency from
# the public available demo system.
source = http
source.url = http://demo.opennms.com/opennms/rest/requisitions/Latency
source.username = demo
source.password = demo

### mapper to set asset longitude and latitude based on a surveillance
category ###
mapper = script
mapper.file = setGeoInfo.groovy
```

# 4.3. JDBC Source

The JDBC source provides the ability to run an SQL Query against an external system and map the result to an OpenNMS requisition.

Para Restaire Description			
source* Set jdbc to use this source for the requisition configuration			
source *driJDBC driver, e.g. org.postgresql.Driver			
source.urlJDBC URL, e.g. jdbc:postgresql://host:port/database			
source.selSQLStatementt			
source.useuser name for database connection			
source.paspassword for database connection			
mapper * Mapper script for changing the requisition. For no operation use echo; for a JSR-223 script set to script			
mapper.fileset mapper is set to script, relative path to your JSR-223 script for modifying the requisition			

The following column-headers will be mapped from the result set to the OpenNMS requisition:

Columentuire Header	edDescription		
Foreigħ_I	dwill be interpreted as foreignId on the node		
Parent_Fo	rdefines Ithe foreignId for the parent node. Used for path outages.		
Parent_Fo	rdefines the foreign Source for the parent node. Used for path outages.		
Parent_No	outages.		
IP_Addres	IP_Addresswill be interpreted as an IP address for a new IP interface on the node		
MgmtType	is interpreted as <pre>snmp-primary</pre> flag and controls how the interface can be used to communicate with the SNMP agent. Valid are P (Primary), S (Secondary) and N (None).		
Interface	Swill the sinterpreted as Interface Status. Value has to be an integer.  Use 1 for monitored and 3 for not monitored.		

Colu <b>i</b> R	•	<b>Description</b>
Node	_Labe	Iwill be interpreted as node label for the node identified by the Foreign_Id
Cat		will be interpreted as a surveillance category for the node identified by the Foreign_Id
Svc		will be interpreted as a service on the interface of the node identified by the Foreign_Id and IP_Address field

This source also supports all asset fields by using <code>Asset\_</code> as a prefix followed by the <code>asset-field-name</code>. The city field of the assets can be addressed like this: yourvalue <code>AS Asset\_City</code> and is not case-sensitive.

Every row of the result set will be checked for the listed column headers. The provided data will be added to the corresponding node. Multiple result rows with matching Foreign\_Id will be added to the same node.



To use additional JDBC drivers, just drop the JAR files into the opennms-pris/lib directory and set the source.driver and source.url accordingly.

# Example configuration to import nodes from phpIPAM MySQL database into OpenNMS

```
### File: phpipam/requisition.properties
# This example connects to an phpIPAM MySQL database and imports the
# data and maps the result an OpenNMS requisition.
# Hint: the MySQL driver has to be manually installed to the opennms-pris/
lib
# directory
source = jdbc
## jdbc source parameter to connect against phpIPAM on MySQL
source.driver = com.mysql.jdbc.Driver
source.url = jdbc:mysql://phpipam.foo.org/phpipam
source.user = user
source.password = secret
source.selectStatement = SELECT \
  id AS Foreign_Id, \
  dns_name AS Node_Label, \
  'P' AS MgmtType, \
```

```
description AS Asset_Description, \
   INET_NTOA(ip_addr) AS Ip_Address, \
   owner AS Cat \
   FROM ipaddresses;

### default no-operation mapper
mapper = echo
```

#### **Example configuration to import nodes from another OpenNMS database**

```
### File: opennms/requisition.properties
# This example connects to an OpenNMS PostgreSQL database and imports the
# data and maps the result a new OpenNMS requisition
source = jdbc
## jdbc source parameter to connect against PostgreSQL
source.driver = org.postgresql.Driver
source.url = jdbc:postgresql://localhost:5432/opennms
source.user = opennms
source.password = opennms
source.selectStatement = SELECT\
  node.foreignId AS Foreign Id, \
  node.nodelabel AS Node_Label, \
  ipinterface.ipaddr AS IP_Address, \
  ipinterface.issnmpprimary AS MgmtType, \
  ipinterface.ipstatus AS InterfaceStatus, \
  assets.description AS Asset_Description, \
  assets.city AS Asset_City, \
  assets.state AS Asset_State, \
  service.servicename AS Svc, \
  categories.categoryname AS Cat \
FROM \
  node LEFT OUTER JOIN ipInterface ON node.nodeId=ipInterface.nodeId \
  LEFT OUTER JOIN ifServices ON ipInterface.ipAddr=ifServices.ipAddr \
  LEFT OUTER JOIN service ON ifServices.serviceId=service.serviceId \
  LEFT OUTER JOIN category_node ON node.nodeId=category_node.nodeId \
  LEFT OUTER JOIN categories ON
 category_node.categoryId=categories.categoryId \
  LEFT OUTER JOIN assets ON node.nodeId=assets.nodeId;
### default no-operation mapper
mapper = echo
```

# 4.4. Merge Source

The merge source allows to merge two provided requisitions accessed by URLs. You can also use provided resources by *PRIS* recursively. The example below shows how to configure the merge requisition for two requisitions A and B.

Para Receptaire	edDescription
source*	set to merge to configure this requisition as a merge requisition
source:A.	นป <sub>ี</sub> RL to the requisition A
source.A.	ussername for access
source.A.	password for access
source*B.	ubtRL to the requisition B
source.B.	ussername for access
source.B.	password for access
source.A.	kile this parameter is present in the config all nodes from requisition A will be present in the resulting requisition.
source.B.	kiethis parameter is present in the config all nodes from requisition B will be present in the resulting requisition.

This source is reading two already defined requisitions via *HTTP* and merges them into one new requisition. By default the resulting requisition will contain all nodes that are present in both requisitions, identified by the foreignId. The A-Node (from requisition A) is enriched with the data from B-Node.

#### Example configuration for a merge requisition

```
### File: merge/requisition.properties
# This example merges two requisitions
source = merge

source.A.url = http://localhost:8000/A
source.A.keepAll

source.B.url = http://localhost:8000/B
source.B.keepAll

### default no-operation mapper
mapper = echo
```

# 4.5. Script Source

This source is provided to give you the flexibility of building your own source without the need to compile from source. The source uses JSR-223 Scripting Engine<sup>1</sup>. The script language can be changed by setting the property source.lang in your requisition.properties file. By default groovy 2.3.3 and beanshell 2.0b5 are ready to use. If you want to use other supported languages, you might need to provide the language jar in the lib folder of PRIS.

Para Reequire	Description
source*	set script to use JSR-223 Script Engine as source
source*fi	leath to script source relative to requisition.properties
source.la	nused to detect the language.
source. <n< td=""><td>ayout representation of the presentation of t</td></n<>	ayout representation of the presentation of t

You can find a working Groovy source in the examples/source/scriptExample directory. A custom parameter name count is passed into the Groovy script.

#### Example configuration to generate a requisition from a Groovy script

```
### File: myGroovySource/requisition.properties
# This example creates a requisition node from a Groovy script
source.file = myGroovySource.groovy
source.count = 3
### default no-operation mapper
mapper = echo
```

## 4.6. XLS Source

The x1s reads an *XLS* spreadsheet file and creates an *OpenNMS requisition* based on the worksheet content.

Para Receptaire	description description
source*	set xls to use the XLS source for this requisition

<sup>1</sup> https://www.jcp.org/en/jsr/detail?id=223

# ParaRecaptive Description source \*file ath of the XLS file to read relative to the requisition.properties source.encencioding of the xls file. Default is ISO-8859-1

The structure of the spreadsheet has to follow these rules. The source reads from a sheet named after the requisition you are requesting. The first row of each sheet is reserved for column names. These column names have to start with certain prefixes to be recognized.

Pref <b>ixeq</b> uire	PrefixequiredDescription		
Node_ *	will be interpreted as node label. It is also used as foreignId if no ID_ header is present.		
IP *	will be interpreted as an IP address as a new interface on the node.		
MgmtType_	is interpreted as <pre>snmp-primary</pre> flag and controls how the interface can be used to communicate with the SNMP agent. Valid are <pre>P</pre> (Primary), <pre>S</pre> (Secondary) and <pre>N</pre> (None).		
ID_	will be interpreted as foreignId for the node. If no foreignId is definded the $Node_{-}$ value is used as foreignId.		
Parent_Fo	Parent_FordefinesItde foreignId for the parent node. Used for path		
	outages.		
Parent_Fo	rdefines the foreign Source for the parent node. Used for path		
	outages.		
Parent_No	outages.		
Interface	swill the interpreted as interface status. Use 1 for monitored and 3 for not monitored.		
cat_	will be interpreted as a surveillance category. Multiple comma- separated categories can be provided. It can be used multiple times per sheet.		
svc_	will be interpreted as a service on the interface of the node. Multiple comma-separated services can be provided. It can be used multiple times per sheet.		

This source also supports all asset-fields by using <code>Asset\_</code> as a prefix followed by the <code>asset-field-name</code>. The city field of the assets can be addressed like this: <code>Asset\_City</code>. This is not case-sensitive.

To add a node with multiple interfaces, add a subsequent row with the same node label (Node\_). This row will be added as a new interface based on the data from the IP\_, MgmtType\_, svc\_ columns.

The order in which the columns are arranged is irrelevant. Also additional columns can be present.



Check the format of cells to avoid problems with data like IP address.

#### Example configuration for the requisition myRouter from an XLS spreadsheet

```
### File: myRouter/requisition.properties
# This example imports devices from a spreadsheet
# named "myRouter" from the myInventory.xls file
# Path to the XLS fils is relative to
# requisitions.properties
source = xls
source.file = ../myInventory.xls

### default no-operation mapper
mapper = echo
```

## 4.7. OCS Source

OCS-Inventory NG is an inventory and software management software. It handles computers and SNMP devices as separate entity types in its APIs. For that reason there are two different sources available to import nodes from OCS. Some parameters are part of both sources and described first.

#### 4.7.1. General OCS Parameters

The following parameters are **required**:

Para Receptaire	edDescription
source*	Set ocs.computers to import OCS computer entities and ocs.devices for OCS SNMP devices
source*ur	1The URL of the OCS web application.
source*us	ArQGS user with rights to access the OCS Soap interface.
source*pa	sThe password for the OCS user with rights to access the OCS Soap interface.

# Para Reception

detailed the data is that the integration is requesting from the *OCS*. It is important to request all the data you want to map into your requisition but not too much, since a higher checksum causes the request to be significantly slower. Read the OCS Web-Services documentation for more information. The default *checksum* for the *default mapper* is 4611.

list, just computers and snmpDevices that are marked with all the tags will be read from the OCS. This feature can be used to tag computers as testing or production.

to. The resulting xml file can be used for debugging or test reasons.

## 4.7.2. Using a source for OCS computers

This source reads computers from an *OCS instance*. It supports all parameters listed as general and the following additions:

• accountinfo = accountinfo data is based on custom fields managed in OCS. These are managed by the *Administrative-Data* section of the *OCS web application*. The name of the custom field is presented in all caps. The value of the field as provided by the user. The ocs.accountinfo parameters supports a list of accountinfo that must be present on the computer. If any of the accountinfo is not present the computer is skipped. To add multiple accountinfo values, separate them with spaces.

# 4.7.3. Using a source for OCS SNMP devices

This source reads snmpDevices from an OCS instance. It supports all parameters listed as general and no additional at the moment.

## 4.7.4. Using a mock source for development

For development and testing there are ocs.computers.replay and ocs.devices.replay sources available. These sources require a file that contains

<sup>&</sup>lt;sup>2</sup> http://wiki.ocsinventory-ng.org/index.php/Developers:Web\_services

the computers or snmpDevices as an *XML* file. The file has also be referenced in the configuration.

#### **Example configuration to import OCS computer into OpenNMS**

```
### File: computers.basic/requisition.properties
# This example imports OCS computer devices into
# an OpenNMS requisition. To convert the OCS
# computer into a requisition the mapper.groovy
# is used.
source = ocs.computers
source.url = https://your-ocs-webapplication.ocs
source.username = ocs-user
source.password = ocs-password
source.checksum = 4611
source.tags =
### mapper to convert OCS computer model into OpenNMS requisition model
mapper = ocs.computers
mapper.ocs.url = https://your-ocs.webapplication.ocs
## Run a custom mapper script
script.file = mapper.groovy
### CATEGORIES ###
mapper.categoryMap =
```

#### Example configuration to import OCS SNMP devices into OpenNMS

```
### File: computers.basic/requisition.properties
# This example imports OCS SNMP devices into
# an OpenNMS requisition. To convert the OCS
# SNMP devices into a requisition the mapper.groovy
# is used.
source = ocs.devices
source.url = https://your-ocs-webapplication.ocs
source.username = ocs-user
source.password = ocs-passowrd
source.checksum = 4611
source.tags =

### run the default mapper for snmp-devices
mapper = ocs.devices
categoryMap =
```

# Chapter 5. Mapper

A mapper can be used to map the result of a source to an OpenNMS Requisition model. The mapper receives the result of the source. The source is not limited in the data model it provides to the mapper. The mapper has to provide an OpenNMS Requisition as its result. If the source provides a custom data model, the mapper has to map it into a Requisition. Some sources provide OpenNMS Requisition directly in a ready-to-use form; in those cases the <a href="mapper">echo.mapper</a> can be used. Complex sources like the <a href="mappers">OCS-Sources</a> provide OCS specific models and require their own specific mappers.

A mapper is configured in the requisition.properties for the requisition.

```
/opt/opennms-pris
### requisitions
### myRequisitionConfiguration
### requisition.properties
```

# 5.1. No-operation echo mapper

The echo mapper is a mapper that forwards the result of the source verbatim. That requires the source to provide a ready-to-use requisition and not a custom model. This mapper does not change the result of the source.

# 5.2. Empty requisition mapper

The null mapper is a special mapper that just provides an empty requisition. This can be useful to handle the entire mapping between the result of the source and the OpenNMS requisition in a script step.

# 5.3. OCS Mapper

Mappers are used to map the bifurcated OCS data model centered around computers and SNMP devices to the unified OpenNMS data model for provisioning nodes, interfaces, services and assets. The OCS integration provides one default mapper for computers and one for SNMP devices out of the box. Additionally it provides for script-based mapping via script steps. The default mappers for OCS are a simple way to map computers and SNMP devices to OpenNMS nodes.

## 5.3.1. OCS Computers

To use this mapper, configure your requisition config to use ocs.computers as mapper. This mapper requires a checksum of 4867 to get all required data. It elects the OCS-Source-IP as management-interface of the node. The black- and whitelisting is applied against the interface. If no interface is valid, the node will have no interfaces and a corresponding log message will be written. The elected management interface is enriched with the interface description, if available. The SNMP and ICMP services are forced onto the management interface. Additionally the comment field of the node assets is used to provide an HTML link to the computer page of the OCS instance. The assets for cpu and operatingSystem will be mapped from the OCS computer too. The computer name is used as both foreignId and nodeLabel.

## Accountinfo to Category Mapper

The default mapper for Computers supports a mapping between OCS Accountinfo data from OCS to OpenNMS surveillance categories. To use this feature add the mapper.categoryMap parameter to the requisition.properties file and reference a properties file following this syntax example:

```
# generic example for a properties file that maps OCS Accountinfo data to
   OpenNMS surveillance categories
ADMINISTRATIVEDATAFILEDNAME.data=OpenNMSCategoryName

# the Accountinfo for ENVIRONMENT is mapped to the OpenNMS surveillance
   category "Production" if the Accountinfo value is set to "Production"
ENVIRONMENT.Production=Production
```

# the Accountinfo for JOB is mapped to the OpenNMS surveillance category
"Mail" if the Accountinfo value is set to "Mailserver"
JOB.Mailserver=Mail

# Accountinfo to Asset Mapper

The Default mapper for Computers supports a mapping between OCS Accountinfo data from OCS to OpenNMS assets. Accountinfo entry values can be used as values for OpenNMS asset fields. To use this feature add the assetMap parameter to the requisition.properties file and reference a properties file following this syntax example:

# generic example for Accountinfo mapping to OpenNMS assets
ADMINISTRATIVEDATAFILEDNAME = OpenNMS-AssetName

```
# The value of the Accountinfo entry "TAG" is mapped to the OpenNMS asset
field "region"

TAG = region

# The value of the Accountinfo entry "SERVERRACK" is mapped to the OpenNMS
asset field "rack"

SERVERRACK = rack
```

#### 5.3.2. OCS SNMP Devices

To use this mapper, configure your requisition config to use ocs.devices as mapper. This mapper requires a checksum of 4099. It validates the IP address of the snmpDevice against the black- and whitelists. For the election of the default an IP filter can be used. If the IP address of the snmpDevice is blocked a log message is written and the node will not have any interfaces. The interface has assigned ICMP and SNMP as services. The foreignId is mapped from the OCS id of the snmpDevice. The nodeLabel is provided by the OCS name of the snmpDevice. The assets for CPU and operating system are mapped against OCS. Additionally a link to the OCS snmpDevice page is added to the asset comment field.

#### 5.3.3. Black- and Whitelists

The OCS Integration supports black- and whitelists to control the selection of the management interface for the node. OCS itself does not define a management interface, it just selects one ip-address as default and maintains a networks-list for every device. For the election of the management interface, two IP filters are implemented in the IpInterfaceHelper class. Both read the black- and whitelist from the requisition configuration folder. Name them <code>blackList.properties</code> and <code>whiteList.properties</code>. Every line in those files is interpreted as an IPLike statement to offer ranges.

# Default ip-filter

This filter accepts every IP address as valid that is not blacklisted. IP addresses that are whitelisted are preferred over unlisted IP addresses.

#### Computers

The first IP address of the ocs-networks-list that is whitelisted is used. If no IP address of the ocs-networks-list is whitelisted, the first IP address that

is not blacklisted is elected as the management interface. If no IP address of the ocs-networks-list qualifies, the ocs-default-ip is checked against the blacklist. If it is not blacklisted, it is elected as the management interface (no interface description will be available). If it is blacklisted, no interface is added to the node. (selectManagementNetwork)

#### **SnmpDevices**

The IP address of an snmpDevice is elected as management interface as long as it is not blacklisted. If it is blacklisted, no interface is added to the node. (selectIpAddress)

## Strict ip-filter "WhiteAndBackOnly"

This filter implements a strict black- and whitelist approach. Computers and snmpDevices are handled independently.

#### Computers

This mode is just accepts IP addresses that are whitelisted and not blacklisted. If there are multiple IP addresses listed on <code>ocs-networks-list</code> that are whitelisted but not blacklisted, the first such one is selected as management IP. If no IP address from the <code>ocs-networks-list</code> passes the black- and whitelist, the <code>ocs-default-ip</code> is tested against the black- and whitelist. If the <code>ocs-default-ip</code> is whitelisted and not blacklisted, it is elected as management-ip. If no IP address matches the black- and whitelist, no interface is added to the node. If the <code>ocs-default-ip</code> is selected, the interface of the node will not contain any additional parameters like description. (selectManagementNetworkWhiteAndBlackOnly)

## SnmpDevices

If the IP address of the snmpDevice is whitelisted and not blacklisted, it is elected as management interface. If the IP address does not pass the lists, no interface is added to the node. (selectIpAddressWhiteAndBlackOnly)

## IPLike expressions in lists

In both lists the <code>IPLike</code> syntax can be used to express IP ranges and wildcards. Follow the <code>IPLike</code> description at <code>IPLIKE</code> documentation <sup>1</sup>.

<sup>1</sup> http://www.opennms.org/wiki/IPLIKE

# 5.4. Script mapper

This mapper is used to give you the flexibility of building your own mapper without the need to compile from source. The source uses JSR-223 Scripting Engine<sup>2</sup>. The script language can be changed by setting the property mapper.lang in your requisition.properties file. The following example runs your script in the the JavaScript Rhino<sup>3</sup> engine:

```
### File: requisition.properties

## source configuration part
source = ...

## Run a no operation mapper
mapper = echo

# run mapper script in JavaScript
mapper.lang=javascript
mapper.file = myJavaScriptSource.js
```

If you don't set the language lang property the script engine tries to detect the language by evaluating the file extension.

```
ParaRequireDescription

mapper* script to use JSR-223 Script Engine as source

mapper.fileath to script source relative to requisition.properties

mapper.landSR-223 Script language by name
```

You can find a working example in *Groovy* in the configs/examples/script.mapper directory.

In addition to any other mapper, a final script mapper can be used by specifying script.file in your requisition.properties` file. The specified script will run after the configured mapper and can be used to transform the mapper's output further.

To specify the scripting language, the script.lang property can be used (see mapper.lang).

https://www.jcp.org/en/jsr/detail?id=223

<sup>3</sup> http://en.wikipedia.org/wiki/Rhino\_%28JavaScript\_engine%29

# Chapter 6. Asset field mapping

The asset field mapping can be used in xls.source and jdbc.source.

OpenNMS requisition asset field mapping		
Asset_additionalhardware		
Asset_address1		
Asset_address2		
Asset_admin		
Asset_assetNumber		
Asset_autoenable		
Asset_building		
Asset_category		
Asset_circuitId		
Asset_city		
Asset_comment		
Asset_connection		
Asset_country		
Asset_cpu		
Asset_dateInstalled		
Asset_department		
Asset_description		
Asset_displayCategory		
Asset_division		
Asset_enable		
Asset_floor		
Asset_hdd1		
Asset_hdd2		
Asset_hdd3		
Asset_hdd4		
Asset_hdd5		
Asset_hdd6		

OpenNMS requisition asset field mapping		
Asset_inputpower		
Asset_latitude		
Asset_lease		
Asset_leaseExpires		
Asset_longitude		
Asset_maintContractExpiration		
Asset_maintContractNumber		
Asset_manufacturer		
Asset_managedObjectType		
Asset_managedObjectInstance		
Asset_modelNumber		
Asset_notifyCategory		
Asset_numpowersupplies		
Asset_operatingSystem		
Asset_password		
Asset_pollerCategory		
Asset_port		
Asset_rack		
Asset_rackunitheight		
Asset_ram		
Asset_region		
Asset_room		
Asset_serialNumber		
Asset_slot		
Asset_snmpcommunity		
Asset_state		
Asset_storagectrl		
Asset_supportPhone		
Asset_thresholdCategory		
Asset_username		

Asset\_vendor

Asset\_vendorAssetNumber

Asset\_vendorFax

Asset\_vendorPhone

Asset\_vmwareManagedEntityType

Asset\_vmwareManagedObjectId

Asset\_vmwareManagementServer

Asset\_vmwareState

Asset\_vmwareTopologyInfo

Asset\_zip

# Chapter 7. Script Steps

After the mapper has delivered its requitition, multiple script steps can be used to customize the result. These script steps can change the requisition initially provided by the mapper. Script steps provide a requisition as their results, which allows the chaining of script steps. Every script step has access to the latest version of the requisition. The first script step reads the requisition from the mapper. The second script step reads the requisition provided by the first script step and so on. Additionally every script step can access the configuration of PRIS and the raw result of the source. The script steps are executed by the JVM following the JSR-223 specification. Therefore all JSR-223 supported languages can be used to write script steps. By default runtimes for Groovy 2.3.3 and Beanshell 2.0b5 are provided out of the box.

Every script step has to provide a Requisition object as its result. For every request of a requisition each script step is reloaded.

Script steps are configured in the requisition.properties for the requisition.

```
/opt/opennms-pris
### requisitions
| ### myRequisitionConfiguration
| ### requisition.properties
### scriptsteps
### default
| ### reverseDNS.groovy
| ### requisitionRename.groovy
| ### IgnoreNodeByCategory.groovy
### custom
### myScript.groovy
```

#### How to add script steps

```
### File: requisition.properties
## source configuration part
source = ...
## Run a no operation mapper
mapper = echo
# run script step
```

```
script.file = ../../scriptsteps/default/requisitionRename.groovy, ../../
scriptsteps/default/IgnoreNodeByCategory.groovy
```

#### **Example script step 1**

```
* This script renames the requisition to the value in the newName
variable.
* If newBuilding is set to true, each node gets the newName set as
building
* /
import org.opennms.pris.model.Requisition
import org.opennms.pris.model.RequisitionNode
logger.info("starting requisitionRename.groovy")
String newName = "myNewRequisitionName"
Boolean newBuilding = false // true
requisition.setForeignSource(newName)
if (newBuilding) {
  for (RequisitionNode node : requisition.getNodes()) {
    node.setBuilding(newName)
  }
}
logger.info("done with requisitionRename.groovy")
return requisition
```

```
for (RequisitionNode node : requisition.getNodes()) {
    if (RequisitionUtils.hasCategory(node, IGNORE_CATEGORY, true)) {
        logger.debug("node '{}' has to be ignored", node.getForeignId())
    } else {
        nodes.add(node)
        logger.debug("node '{}' is ok", node.getForeignId())
    }
}
requisition.unsetNodes()
requisition.withNodes(nodes)
logger.info("done with IgnoreNodeByCategory.groovy")
return requisition
```

```
/**
* This script step sets the nodelabel based on a reverse dns lookup of the
ip interfaces.
* It reverse dns lookups all interfaces for each node until it findes a
dns name for a node.
* If a dns name was found it is set as nodelabel and no other interface of
the nodes will be checked.
* If no dns name was found the nodelabel will be changed.
* /
import org.opennms.pris.model.Requisition
import org.opennms.pris.model.RequisitionNode
import org.opennms.pris.model.RequisitionInterface
logger.info("starting reverseDNS.groovy")
for (RequisitionNode node : requisition.getNodes()) {
  for (RequisitionInterface myInterface : node.getInterfaces()) {
    String ipAddress = myInterface.getIpAddr()
    String dnsNodeLabel =
 InetAddress.getByName(ipAddress).getCanonicalHostName()
    logger.debug("For foreignID '{}' dnsNodeLabel for IP '{}' is '{}'",
 node.getForeignId(), ipAddress, dnsNodeLabel)
    if (!ipAddress.equals(dnsNodeLabel)) {
      logger.info("Using '{}' as NodeLabel for foreignId '{}' based on IP
 '{}'", dnsNodeLabel, node.getForeignId(), ipAddress)
      node.setNodeLabel(dnsNodeLabel)
     break
    }
  }
```

```
}
logger.info("done with reverseDNS.groovy")
return requisition
```

#### **Example script step 4**

```
/**
* This script forces a hard failure if the requisition is empty.
* This can avoid provisioning an empty requisition,
* including removing the existing nodes, on a failure of a source or
mapper.
**/
import org.slf4j.Logger
import org.opennms.pris.model.Requisition
logger.info("starting failOnEmpty.groovy")
logger.debug("Amount of nodes in the requisition '{}'",
 (requisition.getNodes().size()))
if (requisition.getNodes().size() == 0) {
  throw new Exception ("The requisition had no nodes. The
failOnEmpty.groovy script is failing the request on purpose.")
logger.info("done with failOnEmpty.groovy")
return requisition
```

```
/**
* This script provides backwards compatibility with OpenNMS 1.12 in
  regards to Assets.

**/

import org.opennms.pris.model.Requisition
import org.opennms.pris.model.RequisitionNode
import org.opennms.pris.model.RequisitionAsset
import org.opennms.pris.util.RequisitionUtils
import org.opennms.pris.model.AssetField_1_12
import org.opennms.pris.util.AssetUtils

logger.info("starting OpenNMS_Assets_1_12.groovy")

List<RequisitionAsset> assetsToRemove = new ArrayList<>();
```

```
for (RequisitionNode node : requisition.getNodes()) {
   for (RequisitionAsset asset : node.getAssets()) {
       if (asset.getName().equalsIgnoreCase("managedObjectInstance") ||
 asset.getName().equalsIgnoreCase("managedObjectType") ) {
           assetsToRemove.add(asset);
           logger.info("Remove from node '{}' the asset '{}' with the
 value '{}'", node.getNodeLabel(), asset.getName(), asset.getValue());
       } else {
           for (AssetField_1_12 assetField : AssetField_1_12.values()) {
               if (asset.getName().equalsIgnoreCase(assetField.name())) {
                   String assetValue_1_12 =
 AssetUtils.assetStringCleaner(asset.getValue(), assetField.maxLength);
                   if (!assetValue_1_12.equals(asset.getValue())) {
                       logger.info("For node '{}' asset '{}' was
 changed from '{}' to '{}'" , node.getNodeLabel(), asset.getName(),
 asset.getValue(), assetValue_1_12)
                       asset.setValue(assetValue_1_12);
                   break;
               }
           }
      }
  node.getAssets().removeAll(assetsToRemove);
  assetsToRemove = new ArrayList<>();
logger.info("done with OpenNMS_Assets_1_12.groovy")
return requisition
```

Every script step can reference variables from the runtime of PRIS. The following script shows the provided objects:

```
/**
* This sample script step demonstrates all objects provided by the pris
  runtime.
* The objects are casted to there exact type and logged.
**/

import java.nio.file.Path
import org.slf4j.Logger
import org.opennms.pris.model.Requisition
import org.opennms.pris.util.InterfaceUtils
import org.opennms.pris.config.InstanceApacheConfiguration
```

```
logger.info("starting Sample.groovy")
logger.debug("script '{}'", ((Path)script))
logger.debug("data '{}'", ((Object)data))
logger.debug("requisition '{}'", ((Requisition)requisition))
logger.debug("logger '{}'", ((Logger)logger))
logger.debug("config '{}'", ((InstanceApacheConfiguration)config))
logger.debug("config '{}'", ((InterfaceUtils)interfaceUtils))
logger.info("done with Sample.groovy")
return requisition
```

# Chapter 8. Documentation guidelines



Other than writing documentation, you can help out by providing comments about improvements or reporting bugs - head over to the issue tracker for documentation <sup>1</sup> to do that!

For how to build the manual see: readme<sup>2</sup>

The documents use the AsciiDoc format, see:

- Aciidoc Reference<sup>3</sup>
- AsciiDoc FAQ<sup>4</sup>
- AsciiDoc cheatsheet<sup>5</sup>
- AsciiDoc Cheatsheet<sup>6</sup>

Here you can find other resources to get familiar with AsciiDoc, see:

- AsciiDoc User Manual<sup>7</sup>
- AsciiDoc Maven Plugin<sup>8</sup>
- AsciiDoc discussion list<sup>9</sup>
- AsciiDoc issue tracker<sup>10</sup>
- Docbook to AsciiDoc<sup>11</sup>
- How to create handsome PDF documents without frustration <sup>12</sup>

#### The cheatsheets are really useful!

<sup>1</sup> http://issues.opennms.org/browse/PRIS/component/11369

<sup>&</sup>lt;sup>2</sup> https://github.com/OpenNMS/opennms-provisioning-integration-server/blob/master/README.md

<sup>3</sup> http://www.methods.co.nz/asciidoc/

<sup>4</sup> http://www.methods.co.nz/asciidoc/faq.html

<sup>5</sup> http://powerman.name/doc/asciidoc

<sup>6</sup> http://xpt.sourceforge.net/techdocs/nix/tool/asciidoc-syn/ascs01-AsciiDocMarkupSyntaxQuickSummary/single/

http://asciidoctor.org/docs/user-manual

<sup>8</sup> http://asciidoctor.org/docs/install-and-use-asciidoctor-maven-plugin/

<sup>9</sup> https://groups.google.com/forum/?fromgroups#!forum/asciidoc

http://code.google.com/p/asciidoc/issues/list

<sup>11</sup> https://github.com/oreillymedia/docbook2asciidoc

<sup>12</sup> http://blog.rainwebs.net/2010/02/25/how-to-create-handsome-pdf-documents-without-frustration/

### 8.1. Overall Flow

The documentation for the OpenNMS PRIS is organized in as *Maven Module*. After building, the documentation is generated as HTML output on the file system. The output is generated in the target/generated sources folder. Asciidoc documents have the .asciidoc file extension.

The structure is organized as the following:

Note that different ways to add documentation works best for different cases:

- Tutorials and How To's should be published on the OpenNMS Wiki<sup>13</sup>. For example, You want to explain how you used the JDBC source to integrate OpenNMS PRIS with your vendor specific inventory database.
- The documentation you can find in the source code can be characterized as a nonemotional technical documentation which explains concepts in detail and should be complete.

If you want to contribute a patch to the documentation, just fork the project on github <sup>14</sup>. Make your changes in the branch called develop and send us a pull request. After the review of the pull request we will merge it and your change is in the next release.

# 8.2. Important files and folders

Directory	Contents
README.adoc	Description how to build the documentation from source
pom.xml	Maven project settings for the documentation module
src/asciidoc	Folder with adoc source files
src/asciidoc/index.adoc	root file which includes all the document parts
src/asciidoc/images	directory for including images and screenshots in .png or .jpg format
src/asciidoc/images_src	directory for including original format, e.ggraphml

<sup>13</sup> http://wiki.opennms.org

<sup>14</sup> https://github.com/OpenNMS/opennms-provisioning-integration-server

Directory	Contents
src/asciidoc/configs	configuration and script examples
	referenced in the documentation

# 8.3. Headings and document structure

Each document starts over with headings from level zero (the document title). Each document should have an id. In some cases sections in the document need to have id's as well, this depends on where they fit in the overall structure. To be able to link to content, it has to have an id. Missing id's in mandatory places will fail the build.

This is how a document should start:

```
[[unique-id-verbose-is-ok]]
= The Document Title
```

To push the headings down to the right level in the output, the leveloffset attribute is used when including the document inside of another document.

Subsequent headings in a document should use the following syntax:

```
== Subheading
... content here ...
=== Subsubheading
content here ...
```

# 8.4. Writing

Put one sentence on each line. This makes it easy to move content around, and also easy to spot (too) long sentences.

# 8.5. Gotchas

 Always leave a blank line at the end of documents (or the title of the next document might end up in the last paragraph of the document) • As {} are used for Asciidoc attributes, everything inside will be treated as an attribute. What you have to do is to escape the opening brace: \\ { . If you don't, the braces and the text inside them will be removed without any warning being issued!

## 8.6. Links

To link to other parts of the manual the id of the target is used. This is how such a reference looks:

<<community-docs-overall-flow>>

Which will render like: Section 8.1, "Overall Flow"



Just write "see <<target-id>>" and similar, that should suffice in most cases.

If you need to link to another document with your own link text, this is what to do:

<<target-id, link text that fits in the context>>



Having lots of linked text may work well in a web context but is a pain in print, and we aim for both!

External links are added like this:

http://www.opennms.org/[Link text here]

Which renders like: Link text here 15

For short links it may be better not to add a link text, just do:

http://www.opennms.org/

Which renders like: http://www.opennms.org/



It's ok to have a dot right after the URL, it won't be part of the link.

<sup>15</sup> http://www.opennms.org/


# 8.7. Text Formatting

- \_ltalics\_ is rendered as *Italics* and used for emphasis.
- \*Bold\* is rendered as **Bold** and used sparingly, for strong emphasis only.
- +methodName()+ is rendered as methodName() and is used for literals as well (note: the content between the + signs will be parsed).
- `command` is rendered as command (typically used for command-line) (note: the content between the `signs will not be parsed).
- Mono+\+space++d is rendered as Mono+ space +d and is used for monospaced letters.
- 'my/path/' is rendered as my/path/ (used for file names and paths).
- ``Double quoted" (that is two grave accents to the left and two acute accents to the right) renders as "Double quoted".
- `Single quoted' (that is a single grave accent to the left and a single acute accent to the right) renders as 'Single quoted'.

### 8.8. Admonitions

These are very useful and should be used where appropriate. Choose from the following (write all caps and no, we can't easily add new ones):





Which is rendered as:



Tiptext. Line 2.

# 8.9. Images



All images in the entire manual share the same namespace. You know how to handle that.

# 8.9.1. Images Files

To include an image file, make sure it resides in the *images*/ directory relative to the document you're including it from. Then go:

```
image::opennms-logo.png[]
```


Which is rendered as:



## Figure 8.1.

```
.example.odp
image::example.png[example.odp]
```

Which is rendered as:



### Figure 8.2. example.odp

### 8.10. Attributes

Common attributes you can use in documents:  $\{docversion\} * \{docVersion\} - rendered$  as " $\{docversion\} = \{docversion\} = \{docv$ 

These can substitute part of URLs that point to for example APIdocs or source code. Note that opennms-git-tag also handles the case of snapshot/master.

Sample Asciidoc attributes which can be used:

- {docdir} root directory of the documents
- {nbsp} non-breaking space

### 8.11. Comments

There's a separate build including comments. The comments show up with a yellow background. This build doesn't run by default, but after a normal build, you can use

make annotated to build it. You can also use the resulting page to search for content, as the full manual is on a single page.

Here's how to write a comment:

```
// this is a comment
```

The comments are not visible in the normal build. Comment blocks won't be included in the output of any build at all. Here's a comment block:

```
////
Note that includes in here will still be processed, but not make it into
  the output.
That is, missing includes here will still break the build!
////
```

# 8.12. Code Snippets

### 8.12.1. Explicitly defined in the document



Use this kind of code snippets as little as possible. They are well known to get out of sync with reality after a while.

This is how to do it:

If there's no suitable syntax highlighter, just omit the language: [source].

Currently the following syntax highlighters are enabled:

- Bash
- Groovy
- Java
- JavaScript
- Python
- XML

For other highlighters we could add see https://code.google.com/p/google-code-prettify/.

#### 8.12.2. Fetched from source code

Code can be automatically fetched from source files. You need to define:

- component: the artifactId of the Maven coordinates,
- source: path to the file inside the jar it's deployed to,
- classifier: sources or test-sources or any other classifier pointing to the artifact,
- tag: tag name to search the file for,
- the language of the code, if a corresponding syntax highlighter is available.

Note that the artifact has to be included as a Maven dependency of the Manual project so that the files can be found.

The file will be searched for lines including START SNIPPET: {tag} and END SNIPPET: {tag}, the lines between those will go into the output. Be aware of that the tag "abc" will match "abcd" as well. It's a simple on/off switch, meaning that multiple occurrences will be assembled into a single code snippet in the output. This behavior can be user to hide away assertions from code examples sourced from tests.

This is how to define a code snippet inclusion:

```
[snippet,java]
....
component=opennms-examples
source=org/opennms/examples/JmxDocTest.java
classifier=test-sources
tag=getStartTime
```

## Documentation guidelines

This is how it renders:
<pre>component=opennms-examples source=org/opennms/examples/JmxDocTest.java classifier=test-sources tag=getStartTime</pre>